

A. User documentation

The purpose of this project is to propose and implement a system for object localization using a stereo vision – two cameras. The system computes relative position of the cameras to each other using a calibration pattern. Then the user selects the object to track. Different algorithms can be used for tracking. The tracking algorithms available are detection-based and also sequence-based. When the object is found in the view of the both cameras, a position in three dimensional space is estimated. This part of the documentation is focused on the end user. We introduce installation details and manual for program usage.

A.1 Installation guide

This section documents the process of downloading until running the program.

A.1.1 Downloading the code

The code is available at <https://github.com/JankaSvK/thesis>.

A.1.2 Hardware requirements

The software was tested on a system with Intel(R) Core(TM) i5-7300HQ CPU (2.50GHz, 2496 MHz, 4Core), 16GB RAM running Microsoft Windows 10 Enterprise. Minimal requirements are lower, but the computation power reflects on frequency of getting localization results. Also, we tested the program on the Ubuntu 16.04.

Two cameras are needed. We tested using a Logitech V-U0018 and Genius Slim 1322AF. A laptop camera may be used too. Requirements for the cameras are at least 640×320 px resolution and 20 FPS. We advise to turn off the autofocus, as it changes the focal length.

A.1.3 Dependencies

The following packages are required to run the application. We also provide versions of packages used to create and test our implementation.

package	version
Python	3.4.0
NumPy	1.13.3
OpenCV-contrib	3.4.0
Matplotlib	2.1.1
Tkinter	8.6
PIL (with ImageTk module)	1.1.7
dlib	19.10.0

You can easily check the installed versions by running `checkVersions.py` in the directory `helpers/`, which is located in the root of the repository.




Figure A.1: Application window

A.2 First run

In the folder `program/` we find an entry point for our application `Main.py`. The text in this chapter is written with assumption that current directory is the directory `program/`. After starting the application a window will show up (displayed in Figure A.1). With no options provided, the program will run on the first two cameras available.

A.2.1 Calibration

As a first step, calibration is expected. We need a calibration pattern – chessboard (example in the Figure 3.2), which could be printed. For given chessboard, edit values in `program/Config.py`. Change the value of `chessboard_inner_corners` to a number of *inner* corners of your chessboard. For example, classic chessboard 8×8 squares has only 7×7 inner corners, so we enter a tuple `(7, 7)` as a number of inner corners. Also change `chessboard_square_size` to the size of your square in millimeters. It is important to check, if printed chessboard has squares, not rectangles, since the printer can slightly scale the image while preprocessing for printing. Moreover, calibration assumes it is a planar object, so glue it to the box or another solid object.

For calibration we have to provide a rich set of views of the chessboard. It is important to move with it and to capture it from various angles, distances and in different parts of the image. A richer set of views increases robustness of the calibration.

After each successful calibration step you will be notified in the console. After successful stereo calibration, estimated distance between the cameras will be printed. If it does not correspond to the reality, consider a recalibration. If it still did not helped, the user can increase the number of images needed for calibration in the configuration file (be careful, the computation time may increase).

If the calibration finished successfully, the calibration results will be automatically saved in `program/calib_results/`. The files will be saved into three directories, regarding if it is stereo or mono calibration. In case of mono calibration, it will be stored in the folder of corresponding camera. The hierarchy is displayed in the Figure A.2. The naming convention for these files is

```

calib_results/
├── stereo_calib_results/
│   ├── 1/
│   └── 2/

```

Figure A.2: Hierarchy of the directory with saved calibration results

`{year}-{month}-{day}-at-{hour}-{minute}.json`, where the date and time specify the moment when the calibration finished.

A.2.2 Selecting the objects

After successful calibration (calibrated with chessboard, or loaded from a file), the user can initialize the trackers. Under each view of the camera, a button for each object is located.

For tracker initialization, click on the button. The next two clicks in the view of the camera, will specify the bounding box for the object. After initializing trackers in both cameras, localization will automatically start.

If the tracker lost the object, the message is displayed in the camera view. Note that, not all trackers are able to recognise losing the object.

A.2.3 Localization

After initialization of the trackers, localization will start automatically. The results are displayed in the graph on the right. We can rotate the graph by grabbing it by mouse in its window. The dot represents the current position and the line represent the trajectory.

Results from localization are automatically saved at the end of the program in `program/localization_data/`. The naming convention for the files includes the date and time, when was the program closed, i.e it has following form: `{year}-{month}-{day}-at-{hour}-{minute}-{object_id}.json`.

Saved localization data consists of the four columns separated by tabs. Each line represents successful localization. In the first column is the time. In the rest three columns coordinates are stored (x, y, z).

A.3 Extras

Different options may be passed to the program (A.1). In case no option is passed, the program runs on first two available cameras. Firstly, calibration for each camera is done and then stereo calibration. As a tracker KCF is used by default.

A.3.1 Notes for options

- *Videos* – only AVI formats are accepted.
- *Trackers* – as `TRACKER` may be used a name of implemented tracker. Allowed tracker names are: `BOOSTING`, `CORRELATION`, `HSV`, `KCF`, `MEDIANFLOW`, `MIL`, `MOSSE`, `PATTERNMATCHING`, `SIMPLEBACKGROUND`, `TLD`.

Listing A.1: Available options

```
Usage: Main.py [options]

Options:
  -h, --help                show this help message and exit
  --camera_input1=NUMBER    Index of camera to be run as left camera
  --camera_input2=NUMBER    Index of camera to be run as left camera
  -o NUMBER, --number_of_objects=NUMBER
                             Number of objects to be tracked.
  --calibration_results1=FILE
                             Calibration results for the first camera
  --calibration_results2=FILE
                             Calibration results for the second camera
  --stereo_calibration_results=FILE
                             Stereo calibration results
  --video1=FILE             Video recording for the first camera
  --video2=FILE             Video recording for the second camera
  -t TRACKER, --tracker=TRACKER
                             The algorithm used for tracking
  --chessboard=TRIPLE       Calibration chessboard parameters
                             inner_cornersX,inner_cornersY,size
  --bbox=BBBOX              Bounding boxes
```

- *Calibration results* – calibration results from previous runs may be used by specifying path to the file.
- *Chessboard* – the expected format is for example `--chessboard=7,8,22`, where the first two number specify number of inner corners and third is the length of the square side in millimeters.

A.3.2 Capturing the videos

We provide additional script to capture and save videos. The script will automatically capture video from all available cameras and save it into `captured_videos`. The capturing can be exited by pressing the key “q”. The script is available in `helpers/video_capture.py` from the root directory of the repository.

A.3.3 Sample scenarios

```
python3 Main.py – runs the application on first two available cameras
python3 Main.py --video1=path/file.avi --video2=path/file.avi – runs
the application on the videos instead of the cameras
python3 Main.py --tracker=CORRELATION – use a correlation tracker
python3 Main.py --chessboard=7,8,22 – using a chessboard pattern with 7×8
inner corners, each has 22 millimeters long side
python3 Main.py -o2 – setting to track two objects
```